# BottleSim Users' Manual

## Program files (Version 2.6, 06/12/2003)

- BottleSimV2.6.sea (executable for Mac OS 9 and OS X)
- BottleSimV2.6.exe (executable for Microsoft Windows)
- BottleSimV2.6.pdf (users' manual)
- input1.txt (sample allele frequency input file for diploid singlelocus modules)
- input2.txt (sample genotypic data input file for diploid multilocus modules)
- input3.txt (sample population size input file for variable population size modules using asexual/monoecious reproductive systems)
- input4.txt (sample population size input file for variable population size modules using dioecious reproductive systems)
- BottleSim.cpp (source code of BottleSim in C++)

### Description

BottleSim is a computer simulation program for simulating the process of population bottlenecks. The major novelties of the program include:

- 1. implementation of an overlapping-generation model
- 2. ability to simulate a wide range of scenarios regarding changes in population sizes
- 3. fexible settings of reproductive systems

Modules included in this version:

- 1. Diploid singlelocus with constant population size
- 2. Diploid singlelocus with variable population size
- 3. Diploid multilocus with constant population size
- 4. Diploid multilocus with variable population size

An option of generating raw genotypic data output is also available. The raw genotypic data output file contains the genotypic data from the last year of each iteration. The genotypic data output is in GENEPOP (Raymond and Rousset 1995) format. This feature allows users to perform poer analysis of statistical genetic tests.

The degree of generation overlap indicates the percentage of individuals that being assigned a random age value with the longevity limit. The age of individuals that are not assigned randomly is set to zero in year0.

The operation is self-explanatory, details of the algorithm are provided in the references.

#### Input file format

This program can only read **ASCII text files** (e.g. MS-DOS text or text-only).

Sample1 (input1.txt) - allele frequency input file for diploid
singlelocus modules

```
3 --- Number of alleles
0.6 --- Frequency of 1st allele
0.3 --- Frequency of 2nd allele
0.1 --- Frequency of 3rd allele
```

The first line indicates the number of alleles in the input file, frequency of each allele starts from second line as demonstrated in sample input file (input1.txt). .

Sample2 (input2.txt) - multilocus genotypic data input for diploid multilocus modules

```
--- Number of individuals
6
3
                     --- Number of loci
Locus1 Locus2 Locus3 --- List of locus names
ID1 1 4 A D f h
                     --- ID and genotype of 1st individual
                     --- ID and genotype of 2nd individual
ID2 2 9 F J s x
ID3 0 8 B I ? ?
                     --- ID and genotype of 3rd individual
ID4 7 7 T T o z
                     --- ID and genotype of 4th individual
ID5 1 5 C F a a
                    --- ID and genotype of 5th individual
ID6 5 7 G H c d
                    --- ID and genotype of 6th individual
```

The first line indicates the number of individuals in the input file and the second line indicates the number of loci typed for each individual. The third line is a list of locus names. Genotypic data start on the fourth line; each individual has an ID followed by its multi-locus genotype in the same order as the locus name list.

Alleles can be coded as any number or character (0-9, A-Z, a-z) as demonstrated in sample input file (input2.txt). The default missing value is '?'. If the genotype of a locus is unknown, the genotype of that locus should be entered as '? ?' (individual3 - locus3). Locus with one or two unknown alleles will be ignored and not included in the allele frequency calculation.

Sample3 (input3.txt) - population size input file for variable population size modules using asexual/monoecious reproductive systems

```
6 --- Number of years to simulate 0 20 --- Year0, population size = 20 1 10 --- Year1, population size = 10 2 20 --- Year2, population size = 20 3 10 --- Year3, population size = 10 4 30 --- Year4, population size = 30 5 15 --- Year5, population size = 15 6 8 --- Year6, population size = 8
```

The first line indicates the number of years to simulate. Population size settings start from the second line, each line has the year number followed by the population size of the year. YearO indicates the starting population size (founder population).

Sample4 (input4.txt) - population size input file for variable population size modules using dioecious reproductive systems

```
O 30 15 --- Year0, population size = 30, number of female = 15
1 20 10 --- Year1, population size = 20, number of female = 10
2 10 5 --- Year2, population size = 10, number of female = 5
3 6 3 --- Year3, population size = 6, number of female = 3
4 5 2 --- Year4, population size = 5, number of female = 2
5 10 3 --- Year5, population size = 10, number of female = 3
6 8 4 --- Year6, population size = 8, number of female = 4
```

The first line indicates the number of years to simulate. Population size settings start from the second line, each line has the year number followed by the population size and the number of female of the year. YearO indicates the starting population size (founder population).

#### Program limitation

The simulation process of this program is only limited by the amount of memory (RAM) available. (Mac OS 9 users: use command+I to change the amount of memory assigned to the program.)

Other limitations regarding input/output filenames and input data:

- Max. length of input and output filenames = 20 (characters)
- Max. length of locus name = 10 (characters)
- Max. length of individual's ID = 10 (characters)

#### Reference

Kuo C-H, Janzen FJ (2003) BottleSim: a bottleneck simulation program for long-lived species with overlapping generations. Molecular Ecology Notes, submitted.

Raymond M, Rousset F (1995) GENEPOP (version 1.2): population genetics software for exact tests and ecumenicism. Journal of Heredity, 86, 248-249.

#### Contact

Chih-Horng Kuo chkuo@iastate.edu http://www.public.iastate.edu/~chkuo/